

DMC-S1000DGUN-0000-00-00-00-00A-022A-D**Issue 4.0 BREX****Phun Gun - Business rules exchange data module**

Total rules	65	Issue # / In-Work #:	001 / 00	Responsible Partner Company (Enterprise Code):	US Army Materiel Command (AMC) Logistics Support Activity (LOGSA) (1L6T4)
Total @allowedObjectFlag	57	Language / Country:	en / US	Originator (Enterprise Code):	BTAS COE (07GB6)
Total rules w/minimum of 1 value	8	Issue Date (YYYY-MM-DD):	2011-09-15		
Possible validations	65	Issue Type:	new	Security:	Unclassified

BREX DM Reference: [DMC-USARMY-0000-00-00-00-00A-022A-D](#) (United States Army - Business rules exchange data module)

Additional References

- External References -
1. [MIL-STD-3031A](#) (Army Business Rules For S1000D: International Specification For Technical Publications Utilizing A Common Source Data Base) [Digital-PDF]
 2. [TABLE C-I](#) (Information generation) [Digital-XLS]
 3. [TABLE C-II](#) (Authoring) [Digital-XLS]
 4. [TABLE C-III](#) (Identification and status) [Digital-XLS]
 5. [TABLE C-IV](#) (Common constructs) [Digital-XLS]
 6. [TABLE C-V](#) (Content section, schema specific) [Digital-XLS]
 7. [TABLE C-VI](#) (Applicability, attribute values, and training) [Digital-XLS]
 8. [TABLE C-VII](#) (CSDB, DMC, ICN, and DM lists) [Digital-XLS]
 9. [TABLE C-VIII](#) (Comment, version control and interchange) [Digital-XLS]
 10. [TABLE C-IX](#) (PM, BREX, and information management) [Digital-XLS]
 11. [TABLE C-X](#) (Content) [Digital-XLS]
 12. [TABLE C-XI](#) (Page-based presentation) [Digital-XLS]
 13. [TABLE C-XII](#) (IETP presentation) [Digital-XLS]
 14. [TABLE C-XIII](#) (Information processing) [Digital-XLS]
 15. [TABLE C-XIV](#) (SNS and information codes) [Digital-XLS]
 16. [AMC-P 25-31](#) (Preparation of Plans For Technical Publication Verification) [Digital-PDF]

SNS Rules			
#	Code	Description	Title
1.	00 A A B C D E F G H	System SubSystem SubSubSystem SubSubSystem SubSubSystem SubSubSystem SubSubSystem SubSubSystem SubSubSystem SubSubSystem	Phun Gun Body Casing Receiver Assembly Barrel Assembly Trigger Assembly Belt Assembly Slide Assembly Hammer Assembly Safety Plate Safety Plate Release Button

Structure Object Rules			
#	Path	Use	Value
1.	Values are restricted: //@securityClassification	ERROR - Value out of range: (Prohibited inclusion of @securityClassification value other than '01') Gun project has no classified data and shall not use code words. (MIL-STD-3031 #5.9.2.2, #5.59.1.29, and #5.73.2.6)	Single Value: 01, Unclassified
2.	Required use of: //qualityAssurance/firstVerification [@verificationType="tabtop"]	ERROR - Rule violated: (The required element /firstVerification/ attribute verificationType value must be 'tabtop'.) First verification shall be a desktop (tabtop) validation. (MIL-STD-3031 #5.10.2.2)	
3.	Prohibited use of: //@applicRefId	ERROR - Rule Violated: (Prohibited inclusion of attribute applicRefId.) Phun Gun has no applicability requirements and shall not use this structure. (MIL-STD-3031 #5.10.2.7, #5.19.2.9, #5.19.2.24, #5.19.2.27, #5.20.2.8,	

		#5.23.2.2, #5.25.2.2, #5.26.2.1, and #5.37.2.14)	
4.	Required use of: //language [attribute::languageIsoCode="en"]	ERROR - Rule violated: (Within the element /language/, the attribute languageIsoCode includes a value other than "en" (English).) Only American English shall be used. (MIL-STD-3031 #5.11.2.1)	
5.	Prohibited use of: //multimedia	ERROR - Rule violated: (Prohibited inclusion of element /multimedia/.) No multimedia technologies shall be incorporated as this is page-based only. (MIL-STD-3031 #5.12.2.2, #5.16.2.1, #5.151.2.1, #5.151.2.2, #5.151.2.3, #5.151.2.4, and #5.154.2.3)	
6.	Prohibited use of: //foldout	ERROR - Rule violated: (Prohibited inclusion of element /foldout/.) Foldouts shall not be used. (MIL-STD-3031 #5.13.2.1, #5.25.2.1, #5.26.2.3, #5.140.3.2.1, #5.40.5.2, and #5.141.3.2.1 - #5.141.5.2)	
7.	Prohibited use of: //warningsAndCautions	ERROR - Rule Violated: (Prohibited inclusion of the element /warningsAndCautions/.) Warning and caution collections shall not be used. (MIL-STD-3031 #5.17.2.4)	
8.	Values are restricted: //@enterpriseCode	ERROR - Value out of range: (Verify allowed CAGE for attribute enterpriseCode.) Allowed responsible partner company and originator CAGE codes. (MIL-STD-3031 #5.19.2.6 and #5.19.2.7)	Single Value: 07GB6, BTAS COE Single Value: 1L6T4, Army Material Command (AMC) Logistics Support Activity (LOGSA)
9.	Prohibited use of: //dmStatus[systemBreakdownCode functionalItemRef functionalItemCode]	ERROR - Rule Violated: (Prohibited inclusion of element /systemBreakdownCode/, /functionalItemRef/, or /functionalItemCode/.) Use of the elements /systemBreakdownCode/, /functionalItemRef/, /functionalItemCode/, and children shall be prohibited. (MIL-STD-3031 #5.19.2.16 - #5.19.2.18)	
10.	Prohibited use of: //dmStatus/skillLevel	ERROR - Rule Violated: (Prohibited inclusion of the element /skillLevel/.) The use of the element /skillLevel/ in IDSTATUS is prohibited. (MIL-STD-3031 #5.19.2.19)	
11.	Prohibited use of: //dmStatus/productSafety	ERROR - Rule Violated: (Prohibited inclusion of the element /productSafety/.) The element /productSafety/ shall not be used. (MIL-STD-3031 #5.19.2.23 and #5.19.2.24)	
12.	Values are restricted: //reasonForUpdate/@id	ERROR - Rule violated: (The value for attribute id on element /reasonForUpdate/ does not meet the required pattern.) The format for reason for update shall follow the pattern "rfu-001." "rfu-002," etc. (MIL-STD-3031 #5.20.2.4)	Pattern: rfu-\d{3}, RFU identification ("rfu-" with 3 digits)
13.	Prohibited use of: //changeInline[@id]	ERROR - Rule Violated: (Prohibited inclusion of the attribute id on element /changeInline/.) The attribute id on the element /changeInline/ shall not be used. (MIL-STD-3031 #5.20.2.9)	
14.	Prohibited use of: //internalRef/@targetTitle	ERROR - Rule Violated: (Prohibited inclusion of attribute targetTitle on element /internalRef/.) The attribute targetTitle shall not be used. (MIL-STD-3031 #5.21.2.4)	
15.	Prohibited use of: //internalRef[text()]	ERROR - Rule Violated: (Prohibited inclusion of content within element /internalRef/.) Other than attributes and their values, no content shall be allowed within the element /internalRef/. (MIL-STD-3031 #5.21.2.7)	
16.	Prohibited use of: //randomList[@listItemPrefix="pf01"]	ERROR - Rule Violated: (Prohibited inclusion of the value pf01 [simple] for random lists.) Simple lists shall not be	

		used. (MIL-STD-3031 #5.22.2.2)	
17.	Prohibited use of: //figure/graphic[descendant-or-self::hotspot and not (ancestor::illustratedPartsCatalog)]	ERROR - Rule Violated: (Prohibited inclusion of element /hotspot/ outside of the IPD data module.) The use of hotspots shall be limited to IPD only. (MIL-STD-3031 #5.27.2.1 and #5.37.2.29)	
18.	Prohibited use of: //productionMaintData	ERROR - Rule Violated: (Prohibited inclusion of element /productionMaintData/.) The element /productionMaintData/ shall not be used. (MIL-STD-3031 #3.28.2.1)	
19.	Prohibited use of: //thresholdInterval	ERROR - Rule Violated: (Prohibited inclusion of element /thresholdInterval/.) The element /thresholdInterval/ shall not be used. (MIL-STD-3031 #5.28.2.2 and #5.29.2.13)	
20.	Prohibited use of: //zoneRef	ERROR - Rule Violated: (Prohibited inclusion of element /zoneRef/.) The element /zoneRef/ shall not be used. (MIL-STD-3031 #5.28.2.3, #5.29.2.13, #5.54.2.7, and #5.54.2.14)	
21.	Prohibited use of: //accessPointRef	ERROR - Rule Violated: (Prohibited inclusion of element /accessPointRef/.) The element /accessPointRef/ shall not be used. (MIL-STD-3031 #5.28.2.4 and #5.29.2.13)	
22.	Prohibited use of: //@IsarData	ERROR - Rule Violated: (Prohibited inclusion of attribute IsarData.) The attribute IsarData shall not be used. (MIL-STD-3031 #5.28.2.5)	
23.	Prohibited use of: //workArea and not (//dmIdent/dmCode/@infoCode = "870")	ERROR - Rule Violated: (Prohibited inclusion of element /workArea/.) The element /workArea/ shall be used for the Checking unpacked equipment DM. (MIL-STD-3031 #3.28.2.6)	
24.	Values are restricted: //@personCategoryCode	ERROR - Value out of range: (Inclusion of an invalid code, verify the value of attribute personCategoryCode.) The values for the attribute personCategoryCode shall be limited to "Operator," "Maintainer," "Technical Inspector," "Supervisor," and "Safety Person." (MIL-STD-3031 #5.28.2.9)	Single Value: Operator Single Value: Maintainer Single Value: Safety Person Single Value: Supervisor Single Value: Technical Inspector
25.	Values are restricted: //trade	ERROR - Value out of range: (Inclusion of an invalid code, verify the value of element /trade/.) The element /trade/ shall be used and populated with the appropriate MOS trade codes. Trades codes shall be limited to 91F, 91K, and 92Y. (MIL-STD-3031 #5.28.2.10)	Single Value: 91F, Small Arms/Artillery Repairer Single Value: 91K, Armament Repairer Single Value: 92Y, Unit Supply Specialist
26.	Prohibited use of: //supplyDescr[not(@id)]	ERROR - Rule Violated: (Prohibited exclusion of the required attribute id on element /supplyDescr/.) The use of the attribute id on /supplyDescr/ is required. (MIL-STD-3031 #5.28.2.16)	
27.	Prohibited use of: //reqTechInfo	ERROR - Rule violated: (Prohibited inclusion of the element /reqTechInfo/.) The element /reqTechInfo/ shall not be used. All schematics that are used shall be part of the tech manual. (MIL-STD-3031 #5.28.2.11 and #5.28.2.12)	
28.	Prohibited use of: //spareDescr[not(@id)]	ERROR - Rule Violated: (Prohibited exclusion of the required attribute id on element /spareDescr/.) The use of the attribute id on /spareDescr/ is required. (MIL-STD-3031 #5.28.2.18)	
29.	Values are restricted: //@quantityUnitOfMeasure	ERROR - Value out of range: (Prohibited inclusion of a value other than "in" for the attribute quantityUnitOfMeasure.) The attribute quantityUnitOfMeasure shall include the value "in" to represent inches. All measurements shall be in inches only. (MIL-STD-3031 #5.29.2.9 and #5.29.2.10)	Single Value: in, in (inches)
30.	Prohibited use of: //reqCondCircuitBreaker	ERROR - Rule Violated: (Prohibited inclusion of element /reqCondCircuitBreaker/.) The element /reqCondCircuitBreaker/ shall	

		not be used. (MIL-STD-3031 #5.29.2.11 and #5.29.2.12)	
31.	Values are restricted: //@footnoteMark	ERROR - Value out of range: (Prohibited inclusion of an unapproved value for attribute footnoteMark. The value "num" is the only approved value.) Superscript numbers shall be used as footnote markers. (MIL-STD-3031 #5.29.2.14)	Single Value: num, superscripted numbers
32.	Prohibited use of: //levelledPara[position()=1 and position()=last()]	WARNING - Manual verification required: (Check all levelledPara's for single occurrences. Verify the content is clear and does not require additional paragraphs.) A single subparagraph shall be allowed in descriptive data modules. (MIL-STD-3031 #5.32.2.1)	
33.	Prohibited use of: //procedure/*/@skillLevelCode	ERROR - Rule Violated: (Prohibited inclusion of the attribute skillLevelCode.) The attribute skillLevelCode shall not be used within procedural data modules. (MIL-STD-3031 #5.33.2.3)	
34.	Prohibited use of: //proceduralStep/proceduralStep/proceduralStep/proceduralStep/proceduralStep/proceduralStep	ERROR - Rule Violated: (Nested levels of the element /proceduralStep/ has been exceeded.) Step indented shall be restricted to five levels. (MIL-STD-3031 #5.33.2.4)	
35.	Prohibited use of: //proceduralStep[position()=1 and position()=last()]	WARNING - Manual verification required: (Check all proceduralStep's for single occurrences. Verify the content is clear and does not require additional steps.) Single sub-steps shall be allowed. (MIL-STD-3031 #5.33.2.5)	
36.	Prohibited use of: //faultReporting //faultIsolation	ERROR - Rule Violated: (Prohibited inclusion of element /faultReporting/ or the element /faultIsolation/.) The fault schema shall not be used. (MIL-STD-3031 #5.34.2.1-#5.34.2.3)	
37.	Prohibited use of: //isolationProcedure/*/@skillLevelCode	ERROR - Rule Violated: (Prohibited inclusion of attribute skillLevelCode within /isolationProcedure/.) The attribute skillLevelCode shall not be used. (MIL-STD-3031 #5.34.2.5)	
38.	Prohibited use of: //isolationProcedure/*/@independentCheck	ERROR - Rule Violated: (Prohibited inclusion of the attribute independentCheck.) The attribute independentCheck shall not be used. (MIL-STD-3031 #5.34.2.6)	
39.	Prohibited use of: //maintPlanning/*/@skillLevelCode	ERROR - Rule Violated: (Prohibited inclusion of attribute skillLevelCode within /maintPlanning/.) The attribute skillLevelCode shall not be used. (MIL-STD-3031 #5.35.2.2)	
40.	Prohibited use of: //maintPlanning/commonInfo	ERROR - Rule Violated: (Prohibited inclusion of element /commonInfo/ within /maintPlanning/.) The element /commonInfo/ shall be prohibited in MAC. (MIL-STD-3031 #5.35.2.3)	
41.	Prohibited use of: //typeDesignation	ERROR - Rule Violated: (Prohibited inclusion of element /typeDesignation/.) The use of the element /typeDesignation/ shall be prohibited. (MIL-STD-3031 #5.35.2.4)	
42.	Prohibited use of: //crew	ERROR - Rule Violated: (Prohibited inclusion of element /crew/.) The crew schema shall not be used. (MIL-STD-3031 #5.36.2.1 - #5.36.2.5, #5.95.5.2.1 - #5.95.5.2.2, and #5.95.8.2.1)	
43.	Prohibited use of: //illustratedPartsCatalog	ERROR - Rule violated: (Prohibited inclusion of the element /illustratedPartsCatalog/.) The parts (IPD) schema shall not be used. (MIL-STD-3031 #5.37.2.1 - #5.37.2.29, #5.103.3, #5.103.4.2, #5.103.5.2.1, #5.103.10.2.1, #5.103.11.2, #5.103.12.2, #5.103.15.2, #5.103.16.2, #5.103.17.2, and #5.103.18.2.1)	
44.	Prohibited use of: //wiringData	ERROR - Rule violated: (Prohibited inclusion of the element /wiringData/.) The wiring schema shall not be used.	

		(MIL-STD-3031 #5.38.2.1, and #5.102.1.2.1 - #5.102.1.2.3)	
45.	Prohibited use of: //wiringFields	ERROR - Rule violated: (Prohibited inclusion of the element /wiringFields/.) The wiring schema shall not be used. (MIL-STD-3031 #5.38.2.1, and #5.102.1.2.1 - #5.102.1.2.3)	
46.	Prohibited use of: //process	ERROR - Rule violated: (Prohibited inclusion of the element /process/.) Gun project has no process data module requirements. The process schema shall not be used. (MIL-STD-3031 #5.39.2.1 - #5.39.2.12, #5.83.2.1 - #5.83.2.2)	
47.	Prohibited use of: //techRepository	ERROR - Rule violated: (Prohibited inclusion of the element /techRepository/.) Gun project has no technical information repository requirements. The schema shall not be used. (MIL-STD-3031 #5.29.2.15, #5.40.2.1 - #5.40.2.2, #5.41.2.1 - #5.41.2.6, #5.42.2.1 - #5.42.2.5, #5.43.2.1 - #5.43.2.9, #5.44.2.1 - #5.44.2.4, #5.45.2.1 - #5.45.2.4, #5.46.2.1 - #5.46.2.2, #5.47.2.1 - #5.47.2.3, #5.48.2.1 - #5.48.2.6, #5.49.2.1 - #5.49.2.6, #5.51.2.1 - #5.51.2.4, #5.86.2.2 - #5.86.2.5)	
48.	Prohibited use of: //container	ERROR - Rule violated: (Prohibited inclusion of the element /container/.) Gun project has no container data module requirements. The schema shall not be used. (MIL-STD-3031 #5.52.2.1 - #5.52.2.2, #5.88.2.1 - #5.88.2.3)	
49.	Prohibited use of: //learning	ERROR - Rule violated: (Prohibited inclusion of the element /learning/.) Gun project has no training data module requirements. The schema shall not be used. (MIL-STD-3031 #5.53.2.1 - #5.53.2.3, #5.61.2.1 - 5.61.2.3, and #5.154.2.5)	
50.	Prohibited use of: //checkListInfo/title	ERROR - Rule violated: (Prohibited inclusion of the element /title/, within the element /checkListInfo/.) The use of /title/ shall be prohibited in the checklist data module. (MIL-STD-3031 #5.43.2.5)	
51.	Prohibited use of: //checkListIntervals	ERROR - Rule violated: (Prohibited inclusion of the element /checkListIntervals/.) The use of /checkListIntervals/ shall not be allowed. (MIL-STD-3031 #5.43.2.6)	
52.	Prohibited use of: //checkListItem/equip	ERROR - Rule violated: (Prohibited inclusion of the element /equip/, within /checkListItem/.) The element /equip/ shall not be used. (MIL-STD-3031 #5.43.2.12)	
53.	Prohibited use of: //checkListItem[not(name)]	ERROR - Rule violated: (Prohibited exclusion of the element /name/, within /checkListItem/.) The use of the element /name/ within the element /checkListItem/ is required. (MIL-STD-3031 #5.43.2.13)	
54.	Prohibited use of: //displayText/simplePara	ERROR - Rule violated: (Prohibited inclusion of the element /simplePara/, within /displayText/.) The element /displayText/ shall be used to present the human readable applicability statement "ALL." (MIL-STD-3031 #5.44.2.2)	
55.	Prohibited use of: //referencedApplicGroup //applicCrossRefTableRef	ERROR - Rule violated: (Prohibited inclusion of the element /referencedApplicGroup/ or the element /applicCrossRefTableRef/.) Gun project has no cross reference applicability requirements and shall not use the applicCrossRefTableRef structure. (MIL-STD-3031 #5.55.2.1 - #5.55.2.8)	
56.	Prohibited use of: //@applicDisplayClass	ERROR - Rule violated: (Prohibited inclusion of the attribute	

		applicDisplayClass.) The S1000D Gun Project has no applicability requirements. (MIL-STD-3031 #5.55.2.3)	
57.	Prohibited use of: //applicCrossRefTable	ERROR - Rule violated: (Prohibited inclusion of the element /applicCrossRefTable/.) Gun project has no cross reference applicability requirements and shall not use this structure. (MIL-STD-3031 #5.56.2.1 - #5.56.2.3)	
58.	Prohibited use of: //condCrossRefTable	ERROR - Rule violated: (Prohibited inclusion of the element /condCrossRefTable/.) Gun project has no cross reference applicability requirements and shall not use this structure. (MIL-STD-3031 #5.57.2.1 - #5.57.2.5)	
59.	Prohibited use of: //productCrossRefTable	ERROR - Rule violated: (Prohibited inclusion of the element /productCrossRefTable/.) Gun project has no cross reference applicability requirements and shall not use this structure. (MIL-STD-3031 #5.58.2.1 - #5.58.2.2)	
60.	Values are restricted: //dmIdent/dmCode/@modelIdentCode	ERROR - Value out of range: (Verify the value of attribute modelIdentCode.) The only permitted model identification code is "S1000DGUN." (MIL-STD-3031 #5.66.2.1 - 5.66.2.2 and #5.66.2.4 - 5.66.2.5)	Single Value: S1000DGUN, Phun Gun (MI for the Gun project and BREX)
61.	Prohibited use of: //dmIdent/dmCode [@itemLocationCode="T"]	ERROR - Rule violated: (The attribute itemLocationCode includes the prohibited value "T.") The ILC "T" shall not be used. (MIL-STD-3031 #5.72.2.1)	
62.	Prohibited use of: //dmlStatus/dmlRef	ERROR - Rule violated: (Prohibited inclusion of the element /dmlRef/.) The element /dmlRef/ shall not be used. (MIL-STD-3031 #5.74.2.4)	
63.	Prohibited use of: //dmEntry/dmRef/dmRefIdent/identExtension	ERROR - Rule violated: (Prohibited inclusion of the element /identExtension/.) The element /identExtension/ shall not be used in the DMRL. (MIL-STD-3031 #5.74.2.5)	
64.	Prohibited use of: //commentContent	ERROR - Rule violated: (Prohibited inclusion of the element /commentContent/.) The comment data module shall not be used. (MIL-STD-3031 #5.76.2.1 - #5.76.2.14)	
65.	Prohibited use of: //externalPubCode/@pubCodingScheme	ERROR - Rule Violated: (Prohibited inclusion of the attribute pubCodingScheme on element /externalPubCode/.) The inclusion of the attribute pubCodingScheme is prohibited. (MIL-STD-3031 #5.21.2.2)	